

HOW TO UPGRADE OR INSTALL LUMBERJACK SOFTWARE ON A CLIENT PC

If you already have LUMBERJACK software installed on your client pc, and the LUMBERJACK software has been upgraded on the main server, when you try to login you will be told that "...Server software has been upgraded, do you want to upgrade your software now? Yes/No".

If you click [Yes], and the Reps\Disks folder on the main server is shared over the network, then the upgrade will happen automatically.

If the Reps\Disks folder is not shared then you will need to use the latest Lumberjack upgrade CD,

IN THIS DOCUMENT – WHERE YOU SEE 1_4_00 PLEASE READ IT AS 1_5_00.



USING THE LATEST LUMBERJACK UPGRADE CD

Put the CD in the CD-Rom drive


Using either My Computer or Windows Explorer, open the CD-Rom drive.

Open the folder **LJ1_4_00**, and then open the **v5** folder

Run Setup.exe





Ensure that **ONLY** the Client elements check box is selected, then click [OK].



The installation directory defaults to the c:\ drive, if you want it to install to another drive on the Client PC change the drive letter, but ensure that the folder name is still *ljcms* – then click [OK]


Ensure that the drive letter for the Report Location is the same drive as the Installation directory. Then click [OK]



The files are then copied across to the drive specified.


LUMBERJACK

Setup will want to create a Program group called *focom limited*, click [OK]



Once the installation is complete click [OK]

A window will appear showing all the icons within the *focom limited* program group.



Lumberjack Remote Execution will need to be running if you want the Client PC to be able to print reports, or to receive error messages from the Lumberjack server.

It will be easier if Lumberjack Remote Execution is copied to Startup.

INSTALLING LUMBERJACK SOFTWARE ON A CLIENT PC FOR THE FIRST TIME.

If you are install LUMBERJACK client software on a pc for the first time, follow the above steps, but when the process is finished you will need to tell the client software where the LUMBERJACK server is.

Go to Start>Programs>focom limited.

Select Lumberjack Setup – you will be asked a series of questions: click [No] to is this the main server?; [OK] the next two boxes; [Yes] to Icons for all users; [Yes] to Startup icons; [Yes] to Remote Notification; [No] to SawMill, Dialup Buffer, and Email; [OK] the next two boxes.

You will then see the Lumberjack Setup window - enter the IP address or name of the Lumberjack server (just the name – you do not need the path) – click [OK] and close Setup.

